

Quickmap Data Download Manager

These instructions describe how to install and configure the Quickmap data download manager.

The Data Download Manager allows you to setup your server to automatically download data updates when they become available from Custom Software Limited. This works similar to how Windows Updates work, in that you can configure your PC to update automatically, or you can click the *Update Now* button to update manually.


The Data Download Manager can also be configured to automatically copy data updates internally from your server to any number of other standalone computers within your office.

The Data Download Manager is not installed automatically when Quickmap is installed, but can easily be installed by running *DataDownloadServiceSetup.msi* which can be found in the Quickmap data folder after you have installed, or downloaded from http://downloads.quickmap.co.nz/URLDownloadHost/downloads/Qmap_AutoDataUpdate. The Data Download Manager requires Quickmap Version 8.2 or better to have been installed.


Install instructions

Before starting the install, check you are running Quickmap Version 8.2 or better on your PC. The Quickmap version number is displayed on the title bar when you run Quickmap.


To install Data Download Manager, download the latest version from http://downloads.quickmap.co.nz/URLDownloadHost/downloads/Qmap_AutoDataUpdate by clicking on the above URL, or pasting it into your web browser.



Select *Show in folder* after it has downloaded.




Right mouse click on *DataDownloadService.zip* and choose *Open with Windows Explorer*.




Copy the zip file contents *DataDownloadServiceSetup.msi* to a temporary folder (e.g. *C:\Temp*) or the Quickmap data folder. If *DataDownloadServiceSetup.msi* already exists in the Quickmap data folder, then overwrite this file.


Double click on the *DataDownloadServiceSetup.msi* extracted from the zip file.
e.g.




Click Next




Click I accept then Next




Click Next




Enter the registration key supplied to you by Custom Software Limited, and click Next



Click the Next button



Click Install button



Click the Finish button.




Using Data Download Manager


Double click on the Quickmap Data Download Manager on your desktop.




To check for updates, click the *Check Now...* button.




The Data Download Manager keeps 2 full backups of your Quickmap data folder to allow you to restore if a problem is encountered with the download.



After the backup has completed, the download will start.



When the data has been downloaded from Custom Software Limited, it will apply the updates to your Quickmap data folder.




Note that in order for the Data Download Manager to apply the updates, it will automatically close any instances of Quickmap that are accessing the Quickmap data folder, to avoid problems with files being in use when it applies the update.

If the Quickmap data is already up-to-date, the Data Download Manager will report *No updates found to install*.

Automatic Data updates

The Data Download Manager runs as a service, and can be set to check for updates daily, so that you do not need to manually check for updates.


To enable automatic updates, tick the *Install data updates automatically* check box. You can also set what time to download and install the updates, as circled below.




Updating Quickmap from a local server

The *Data Download Manager* also supports updating standalone computers by automatically copying files from the Quickmap data folder on your server to other computers. Under this scenario, you would typically setup your server to update over the Internet from Custom Software, and local computers on your **Intranet** updated from your server.


To install the Local Server option, install *DataDownloadServiceSetup.msi*




And on the Data Download Source form, Select *Local Server*




Click Next



Click the Install button.




Click the Finish button




Double click on the Quickmap Data Download Manager on your desktop.




Click the Local Server radio button.



Click the browser button, and browse to the location of Quickmap on the server that has the up-to-date Quickmap data.



To update, click the Check Now button



The Data Download Manager will copy Quickmap data files from the server to your local PC.

